

Forum: Aide - Recherche de logiciels

Topic: lire des videos réalisées sur appareil Kodak Easyshare C330

Subject: Re: lire des videos réalisées sur appareil Kodak Easyshare C330

Publié par: MarillionKid

Contribution le : 26/07/2009 16:48:54


Pour Daddysnak,

Petit additif.

Tu peux faire le tout en une seule opération. A la configuration figurant sur mon image précédente, tu rajoutes les opérations suivantes.

Fichier(s) attaché(s):

Super 2.jpg (96.03 KB)



The screenshot shows the SUPER software interface with the following settings and annotations:

- Step 1:** Select the Output Container: AVI
- Step 2:** Select the Output Video Codec: XviD
- Step 3:** Select the Output Audio Codec: mp3
- Encoding Options:** MEncoder selected, RealProducer unselected.
- VIDEO Section:** Video Scale Size: NoChange; Aspect: 16:9; Frame/Sec: 20; Bitrate: 1008 kbps; Options: Hi Quality, Top Quality, Stretch It, 48K Audio, H264 Profile, Crop / Pad, Other Opts.
- AUDIO Section:** Sampling Freq: 48000; Channels: 2; Bitrate: 128 kbps; DVD Language: default.
- OUTPUT Section:** Encode to File Format: AVI; Use Video Codec: XviD, Size & Aspect as input, 1008 kbps, 20 fps; Use Audio Codec: mp3, Stereo, 128 kbps, 48000 Hz, AudioStream [default] selected.
- DirectShow Options Panel:** Logo Watermark: 1. Watermark= Disabled; File Join: unchecked; Various Video Effects: Slow Motion, Fast Motion, Flip Horizontal, Flip Vertical, Reverse Play, Turn Right (selected), Turn Left, Turn 180; Invert Colors: Y, U, V, Convert To Black & White; Fade In, Fade Out, Clip Info: unchecked.

Annotations:

- Red circle 1 points to the **DirectShow Decode** checkbox.
- Red circle 2 points to the **DirectShow Options** panel.
- Red circle 3 points to the **Turn Right** radio button.
- A yellow box labeled **3): au choix** is positioned above the Turn Right option.